

**@@@@@ ENGLISH INSTRUCTIONS @@@@@**

Thank you for your interest in PCX1000!

If you have downloaded a DEMO version from our web page, you must have received the necessary login information, activation codes and upgrade activation numbers to evaluate this software. Please check your e-mail, or register again with a valid e-mail address if you don't have this data. It will be necessary to make the DEMO version functional.

You will receive

**PCX1000-Light / Activation Code v.7.1**

**UPGRADE to PCX1000-Pro / Activation Code v.7.1**

for QT-6000, TE-7000/8500, SPB, MPS and Multi-Warehouse

**INVENTORY Activation Code**

**How To Install the DEMO:**

- 1) Unzip the INSTALL file by double clicking on it.
- 2) The files will be placed in drive C:\ under the release number folder (for example c:\7105112412)
- 3) After the files have unpacked go to the folder where the files were unzipped and double click on the AUTORUN.EXE file.
- 4) Choose the options from the Menu to install.
- 5) Please use the default directory chosen by PCX1000, don't change the install directory.
- 6) The default directory should be C:\Equisoft\PCX1000.
- 7) IMPORTANT: if this is the first time you install PCX1000 on your PC, you will need to install the new HARDLOCK Drivers before executing PCX1000. Select the option in the installation menu.
- 8) After the software is installed you can run PCX1000 from the Start menu and going to the EQUISOFT Group created in your Programs menu
- 9) If you receive the error message: 'Cannot find ///Fast hardlock driver' you need to return to step #7 and install the HDD32.EXE dirvers.
- 10) The FIREBIRD SERVER will automatically load. At this point choose YES to launch the database server. You can also choose YES ALWAYS. FIREBIRD-Server is vital to run PCX1000, so it will have to open every time you run the software.

### **Activating the DEMO:**

- 1) After the installation has finished, you will be prompted to Activate you software.
- 2) The default company name will be set to "DEMO" in full caps. (don't change this).
- 3) Additional information like Owner and other fields may be left blank.
- 4) Enter the ACTIVATION CODE for the DEMO has been supplied to you by e-mail. Press F10 after typing in your Activation Code.
- 5) The next screen will ask you to create the ADMINISTRATOR of the System. Please select YES, as you need to have FULL access to all menus in this DEMO. If you don't select YES in this section, you will need to reinstall the software and start from step #1) of this section. You will have no access to any menus and all buttons will be grayed out.
- 6) Enter a CODE (password) for the administrator (this can be alphanumeric and will be your password to access the software). Example: 123ABC, and press enter.
- 7) The INITIALS for the Administrator will be ADM, you can change them at you will.
- 8) The NAME for the Administrator can also be changed at your will.
- 9) Click on the green check mark or press F10 / OK to save.
- 10) After the ADMINISTRATOR is created you can either continue adding more users with different access rights, or press ESC.

**You are now ready to evaluate the software. PCX1000-Light is the default level at this point!**

**To upgrade from Light to PROFESSIONAL, pleas go to the Utilities Menu, select System Parameter, click on System TAB and enter the Activation Code in the Professional field, supplied to you by e-mail.**

**To enable the INVENTORY module, pleas go to the Utilities Menu, select System Parameter, click on System TAB and enter the Activation Code supplied by e-mail, in the Stock Ctr field**

Please keep in mind this DEMO will be 100% functional with all features available in PCX1000-Light. To evaluate all ECR's ranging from TE-22000 to QT-6000 without limitations, activate PCX1000-Professional, by following the steps indicated in the previous paragraph.

The only limitations you will find in this DEMO are the PLU's you can poll from the ECR (max 20) and the number of transactions shown on a report will be limited to a maximum of 20.

For further instructions, please use the on line HELP (by pressing F1 in any available screen), or have a look at the complete manual available for download on the PCX1000 web. You can also find helpful bulletins in our PCX1000 - Features section on the web.  
[www.equitron.com/PCX1000/download.htm](http://www.equitron.com/PCX1000/download.htm)

Should you need further help, please don't hesitate to send us an e-mail to:  
[PCX1000@equitron.com](mailto:PCX1000@equitron.com)

Thank you for your time and interest in evaluating our product.

Equitron S.A.